

Cheat-Sheet - tmux Terminalmultiplexer

By: tim@gremalm.se
 http://tim.gremalm.se
 2013-10-17



```

-rw-rw-r-- 1 usr usr 11372 16 jul 15.15 websock.js
-rw-rw-r-- 1 usr usr 5978 16 jul 15.15 webutil.js
-rw-r--r-- 1 usr usr 16384 1 okt 20.48 .webutil.js.swp
-rw-rw-r-- 1 usr usr 5170 16 jul 15.15 wsirc.js
-rw-rw-r-- 1 usr usr 14345 23 jul 16.00 wstlnet.js
-rw-r--r-- 1 usr usr 16384 1 okt 20.48 .wstlnet.js.swp
-rw-rw-r-- 1 usr usr 25805 24 jul 11.46 VT100.js
-rw-r--r-- 1 usr usr 16384 1 okt 20.48 .VT100.js.swp
usr@hostname:/var/www/mysite/include$

wstlnet.js VT100.js util.js webutil.js ../wstlnet.html ../style.css
341 str = '\b'; break;
342 case 65307: // Escape
343 str = '\x1b'; break;
344 case 65361: // Left arrow
345 str = '\x1b[D'; break;
346 case 65362: // Up arrow
347 str = '\x1b[A'; break;
348 case 65363: // Right arrow
349 str = '\x1b[C'; break;
350 case 65364: // Down arrow
351 str = '\x1b[B'; break;
352 case 100045: // Insert
353 str = '\x1b[@'; break;
354 case 100046: // Delete
355 str = '\x1b[P'; break;
356 case 100036: // Home
357 str = '\x1b[H'; break;
358 case 100035: // End
359 str = '\x1b[4~'; break;
360 case 100033: // Page Up
361 str = '\x1b[5~'; break;
362 case 100034: // Page Down
363 str = '\x1b[6~'; break;

NORMAL /var/www/mysite/include/wstlnet.js unix utf-8 sh 63% 352:21
0:3.1 hostname 192.168.0.3 173.194.70.138 1:ssh 2:bash 3 > IDE 0.02, 0.04, 0.00 Tue
    
```

```

usr@hostname:~/tempprojects/websockify$ ls -l
total 84
-rw-rw-r-- 1 usr usr 1278 16 jul 11.43 CHANGES.txt
drwxrwxr-x 2 usr usr 4096 16 jul 15.14 docs
drwxrwxr-x 4 usr usr 4096 16 jul 11.43 include
-rw-rw-r-- 1 usr usr 612 16 jul 11.43 LICENSE.txt
-rw-rw-r-- 1 usr usr 153 16 jul 11.43 Makefile
-rw-rw-r-- 1 usr usr 56 16 jul 11.43 MANIFEST.in
drwxrwxr-x 3 usr usr 4096 16 jul 11.43 other
-rw-rw-r-- 1 usr usr 5955 16 jul 11.43 README.md
-rwxrwxr-x 1 usr usr 424 16 jul 11.43 rebind
-rw-rw-r-- 1 usr usr 2887 16 jul 11.43 rebind.c
-rw-rw-r-- 1 usr usr 2084 16 jul 11.48 rebind.o
-rwxrwxr-x 1 usr usr 6237 16 jul 11.48 rebind.so
-rwxrwxr-x 1 usr usr 82 16 jul 11.43 run
-rw-rw-r-- 1 usr usr 1247 16 jul 11.43 setup.py
drwxrwxr-x 2 usr usr 4096 16 jul 11.43 tests
drwxrwxr-x 2 usr usr 4096 16 jul 11.45 websockify
lrwxrwxrwx 1 usr usr 3 16 jul 11.43 websockify.py ->
run
-rw-rw-r-- 1 usr usr 3387 16 jul 11.43 wsirc.html
-rw-rw-r-- 1 usr usr 2438 16 jul 11.43 wstlnet.html
usr@hostname:~/tempprojects/websockify$
usr@hostname:~/tempprojects/websockify$ ./run 2023 --w
ap-mode=respawn 173.194.70.139:23
WebSocket server settings:
- Listen on :2023
- Flash security policy server
- No SSL/TLS support (no cert file)
- proxying from :2023 to 173.194.70.139:23
1: 192.168.0.9: Plain non-SSL (ws://) WebSocket conne
ction
1: 192.168.0.9: Version hybi-13, base64: 'False'
1: connecting to: 173.194.70.139:23
    
```

Pane (Split)	
split-window	[-l size -p percentage] [-t target-pane] [shell-command]
" Split-window	-h (Split pane horizontally)
% split-window	-v (Split pane vertically)
list-panes	
Up select-pane	select-pane -U
o select-pane	[-t target-pane]
select-pane -t :.+	(Select next pane)
; last-pane	(Select previously active pane)
M-Up resize-pane	resize-pane -U 5
^Up resize-pane	resize-pane -U
resize-pane	[-t target-pane] [adjustment]
	-DLRU Doqn/Left/right/Up
	tmux resize-pane -l -t 2 20
q display-panes	(Show pane numbers visually over panes)
{ swap-pane	swap-pane -U
} swap-pane	swap-pane -D
swap-pane	[-s src-pane] [-t dst-pane]
	-d (Instructs tmux not to change the active pane)
^o rotate-window	(Swap location of panes)
Space next-layout	(Swap layout of panes)
join-pane	[-l size -p percentage] [-s src-pane] [-t dst-pane]
joinp	joinp
joinp -s :2	(Move window 2 into a new pane in the current window)
joinp -t :1	(Move the current pane into a new pane in window 1)
:	break-pane [-t target-pane] (Break pane to a new window)
t clock-mode	[-t target-pane]
^d	(Close current pane)
x kill-pane	[-t target-pane]

Copy-/History - Mode	
[copy-mode Starts copy-mode
PageUp	copy-mode -u Starts copy-mode and scroll up
]	paste-buffer
list-buffers	Shows a list of copy-buffers

Copy-/History - Settings	
setw -g mode-keys vi	Configure tmux to use vi-style navigation in copy mode
setw -g mode-keys emacs	Configure tmux to use emacs-style navigation in copy mode

bind p paste-buffer	
bind-key -t vi-copy 'v'	begin-selection
bind-key -t vi-copy 'y'	copy-selection

Copy-/History - Keys		
vi	emacs	Function
q	Escape	Quit mode
j	Down	Cursor down
k	Up	Cursor up
h	Left	Cursor left
l	Right	Cursor right
J	C-Down	Scroll down
K	C-Up	Scroll up
C-f	Page down	Next page
C-b	Page up	Previous page
:	g	Goto line
g	M->	Top of history
G	M-<	Bottom of history
	0C-a	Start of line
	^	M-m Back to indentation
	\$	C-e End of line
w	M-f	Next word
e		End of word
b	M-b	Previous word
Space	C-Space	Start selection
v	R	Rectangle toggle
Escape	C-g	Clear selection
Enter	M-w	Copy selection
/	C-y	Paste buffer
p	C-s	Search
n	n	Search again
N	C-r	Search backward

Session	
new-session	new [-s session-name] tmux -S /tmp/shared_session_socket chmod 777 /tmp/shared_session_socket
attach-session	attach [-t target-session] -d (Re-attach and attached session (detaching it from elsewhere)) -r (Read only) tmux -S /tmp/shared_session_socket attach
s	list-sessions ls
d	detach-client [-s target-session]
z	suspend-client
\$	rename-session [-t target-session] new-name
kill-session	[-t target-session]

Window (Tab)	
c	new-window [-n window-name] [shell-command]
list-windows	lsw [-t target-session]
w	choose-window (Same as list, but a menu)
7	select-window [-t target-window] (Select window number 7)
n	next-window [-t target-session]
p	previous-window [-t target-session]
l	last-window [-t target-session] (Select last selected window)
i	display-message (Show information about current window and pane)
f	find-window [-t target-window] match-string (Freetext search through windows)
.	move-window movew [-s src-window] [-t dst-window]
,	rename-window [-t target-window] new-name
&	kill-window [-t target-window]

Mouse mode	
set -g mouse-select-window on	Select window
set -g mouse-select-pane on	Select pane
set -g mouse-resize-pane on	Resize pane
setw -g mode-mouse on	Select text

Statusbar Color	
set-option -g status-bg colour235	
set-option -g status-fg white	
set-option -g window-status-bg colour35 colour35	
set-option -g window-status-current-bg colour25	
set-option -g window-status-current-fg black	
Center the window list	
set -g status-justify centre	

Terminal settings	
Set charset	set-window-option -g utf8 on
Set mode to 256color mode	set -g default-terminal "screen-256color"
Force tmux to use 256 colors	tmux -2
Force tmux to use 88 colors	tmux -8
Enable activity alerts	setw -g monitor-activity on
	set -g visual-activity on
Clock	set-window-option -g clock-mode-style [12 24]
	set-window-option -g clock-mode-colour colour

Prompt	
Tmux command-prompt	^b :
Autocompletion in tmux command-prompt	Tab

Keybinding	
? list-keys	See keybinding
Change prefix (From Ctrl+B to Ctrl+A)	unbind C-b
	set -g prefix C-a
Bind-key	bind-key
	-r (Indicates this key may repeat)
Keys	[A-Z]
	Ctrl key [C-] or [^]
	Alt key (Meta) [M-]
	[F1-F20]
	Up, Down, Left, Right
	End, Home, IC (Insert), NPage (Page Up), PPage (Page Down)
	BSpace, BTab, DC (Delete), Enter, Escape, Space, and Tab.
To bind the '***' or '***' keys, quotation marks are necessary:	bind-key *** split-window
	bind-key *** new-window
Send keys	send-keys [-t target-pane]
	send-prefix [-t target-pane]

All tmux-commands can be accessed through tmux prompt (:Command) or by the CLI (tmux Command), and could be mapped to a keybinding (:bind k Command). In a session with several attached clients, tmux will set the resolution to the least common resolution. Consoles Font is used in Terminal. Powerline is Used for tmux and vim.